



How To Install MetaMask
And Connect To Bitkub Chain Mainnet



Contents


How to Download and Install MetaMask	2
Download and Install MetaMask	2
Connect to wallet	6
Connect to wallet – Have wallet and seed phrase	11
How to Connect to Bitkub Chain Mainnet	15
Connect to Bitkub Chain Mainnet	15




How to Download and Install MetaMask

1. Download and Install MetaMask

1.1 Enter <https://metamask.io> on your web browser.




1.2 Click on [Download](#).




HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



1.3 Click on [Install](#) MetaMask.




After clicking on [Install](#) MetaMask, it will lead you to your web browser add-ons/ extensions. In this case, we are using Google Chrome.




HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



1.4 Click [Add to Chrome](#) button.




1.5 Click [Add extension](#). After adding the extension, MetaMask will be available on your Chrome extension tab. **Please refer to step number (3.7) on how to pin Metamask extension to your browser.**




HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



1.6 After adding the MetaMask extension, a MetaMask page will be shown to start using MetaMask's wallet. Now Click [Get Started](#).



1.7 MetaMask will ask you to [Import wallet](#) or [Create a Wallet](#).




HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET




2. Connect to wallet

2.1. For instance, if you do not have a wallet and seed phrase, Click [Create a Wallet](#).

But if you already have a wallet and seed phrase, ***please proceed step number 3.***



2.2. Click [I Agree](#).



HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



2.3 Enter your **password** and **confirm your password** and click on the Checkbox to agree with the **terms of use**.

METAMASK

< Back

Create Password

New password (min 8 chars)

Confirm password

I have read and agree to the [Terms of Use](#)

Create

2.4 Click **Create**.

METAMASK

< Back

Create Password

New password (min 8 chars)

Confirm password


I have read and agree to the [Terms of Use](#)

Create

HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



2.5 Click on “**CLICK HERE TO REVEAL SECRET WORDS**” and write down the words you see on a paper in a correct order



Note: These words are called **Seed phrases. You have to enter a seed phrase in order to import your wallet into another web browser or mobile application. So please make sure that no one knows your seed phrase and make sure not to lose your seed phrase paper.*


2.6 Enter **your seed phrase** in the correct order.




HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



2.7 Click **Confirm**.




2.8 Click **All Done**.



HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



2.9 **Congratulations!** Your MetaMask wallet is ready to use.




HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET




3. Connect to wallet – Have wallet and seed phrase

3.1 If you already have a wallet and seed phrase, Click [Import wallet](#).



3.2 Click [I Agree](#).



HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



3.3 Enter your **Seed phrase, password** and click on the Checkbox to agree with the **terms of use**.

METAMASK

< Back

Import an account with seed phrase

Enter your secret phrase here to restore your vault.

Seed phrase

Show seed phrase

New password (min 8 chars)

Confirm password

I have read and agree to the [Terms of Use](#)

Import

3.4 Click **Import**.

METAMASK

< Back

Import an account with seed phrase

Enter your secret phrase here to restore your vault.

Seed phrase

Show seed phrase

New password (min 8 chars)

Confirm password


I have read and agree to the [Terms of Use](#)

Import


HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



3.5 Click **All Done**.





3.6 **Congratulations!** Your MetaMask wallet is ready to use.



HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



3.7 Click on the **pin icon** to pin MetaMask to your Chrome browser.




Congratulations! You can now use your MetaMask by clicking the icon on the top right corner of your web browser.



How to Connect to Bitkub Chain Mainnet

1. Connect to Bitkub Chain Mainnet

1.1 Open [MetaMask](#) wallet on your web browsers.




Note: MetaMask is a software cryptocurrency wallet used to interact with any Blockchains. It allows users to store and manage account keys, broadcast transactions, send and receive cryptocurrencies and tokens.


HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



1.2 Click **Network** and select **Custom RPC**.




HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



1.3 Enter **Bitkub Chain Mainnet information** as follows in the input fields and then click **Save**.

Network Name: Bitkub Chain Mainnet
New RPC URL: https://rpc.bitkubchain.io
Chain ID: 96
Currency Symbol: KUB
Block Explorer URL: https://bkcsan.com

HOW TO INSTALL METAMASK AND CONNECT TO BITKUB CHAIN MAINNET



1.4 **Congratulations!** You have now successfully connected to Bitkub Chain.

